

GLYCOL COOLING SYSTEM DRAFT

MODEL DESCRIPTION DOCUMENT (MDD)

Version – DRAFT v0.1



AUGUST 8, 2016

PREPARED FOR:
DS FEDERAL FDA
ATTN: CURTIS MILLER



PREPARED BY:
DIGNITAS TECHNOLOGIES, LLC
3504 LAKE LYNDA DR., SUITE 170
ORLANDO, FL 32817

DOCUMENT REVISION HISTORY

Version	Description	Date
0.1	Draft	08/08/16

TABLE OF CONTENTS

DOCUMENT REVISION HISTORY.....	i
TABLE OF FIGURES.....	iii
TABLE OF TABLES.....	iii
1 MODEL OVERVIEW	1
1.1 DESCRIPTION	1
1.2 REFERENCES.....	1
1.3 MODEL VERSION AND HISTORY.....	1
1.4 MODEL SUMMARY	2
2 UNITY PACKAGE.....	3
2.1 IMPORTING THE UNITY PACKAGE.....	3
3 MODEL ATTRIBUTES	4
3.1 POLYGON ALLOCATION	4
3.2 LEVEL OF DETAIL (LODS)	4
3.3 TEXTURE MAPS	4
3.3.1 COLOR MAP.....	4
3.3.2 NORMAL MAP	5
3.3.3 AMBIENT OCCLUSION MAP	6
3.4 SENSOR VIEWS.....	6
3.5 MODEL STATES.....	6
3.6 SKELETAL STRUCTURE	6
4 ANIMATIONS.....	6
5 VERIFICATION APPROACH.....	7

5.1	RUNTIME SYSTEMS	7
6	LIMITATIONS	7
7	CONTACT INFORMATION	7

TABLE OF FIGURES

Figure 1	Glycol Cooling System Model (Unity Render).....	1
Figure 2	Glycol Cooling System Origin on Cartesian X, Y, Z Coordinate System (Maya Software Render) ..	2
Figure 3	Glycol Cooling System (Unity View)	2
Figure 4	Unity Import Package.....	3
Figure 5	Glycol Cooling System Color Map	4
Figure 6	Glycol Cooling System Normal Map.....	5
Figure 7	Glycol Cooling System Ambient Occlusion Map	6

TABLE OF TABLES

Table 1	Model Revision History.....	1
Table 2	Model Summary.....	2
Table 3	Polygon Allocation.....	4

1 MODEL OVERVIEW

1.1 DESCRIPTION

- Refrigeration unit that chills food grade anti-freeze (Glycol)

1.2 REFERENCES

- 3D_Model_Development_Process.docx
 - The 3D model development process details Dignitas Technologies’ procedure for building 3D models.



Figure 1 Glycol Cooling System Model (Unity Render)

1.3 MODEL VERSION AND HISTORY

Information about the model version can be found in the “Model_Version.txt” file located in the model’s directory (same directory the model’s .fbx file is located).

Table 1 Model Revision History

Version	Description	Date
0.1	Initial release of the draft Glycol_Cooling_System.fbx	08/08/16

1.4 MODEL SUMMARY

Table 2 Model Summary

Model Name	Glycol_Cooling_System.fbx
Model Units	Meters
Coordinate System	Cartesian X, Y, Z (see Figure 2 below)
Model Origin	Origin is located at center mass. (0, 0, 0) (See figure 2 below)
Model Orientation Runtime	Forward: Positive Y Up: Positive Z
Model Orientation Maya	Forward: Positive Z Up: Positive Y




Figure 2 Glycol Cooling System Origin on Cartesian X, Y, Z Coordinate System (Maya Software Render)

This model was imported into Unity 5.3 to verify the model (see Figure 3 below).



Figure 3 Glycol Cooling System (Unity View)

2 UNITY PACKAGE

2.1 IMPORTING THE UNITY PACKAGE

1. Download the “Glycol_Cooling_System_08-08-16.unitypackage” file from Google Drive
2. Open the “Milk Factory” Unity Project in Unity 5
3. In the top menu bar go to “Assets → Import Package → Custom Package...”
4. A window should pop up showing you the contents of the Unity Package being imported
 - a. This Unity Package should look like this:




Figure 4 Unity Import Package

5. Press “Import” and the model and materials will be placed into the Assets section.
6. Make sure that when dragging the model into the scene that you select the “Prefab_Glycol_Cooling_System.prefab” instead of the FBX as the prefab has the materials stored on it correctly.

3 MODEL ATTRIBUTES

3.1 POLYGON ALLOCATION

Polygon allocation is the number of triangles and vertices for a given state and Level of Detail (LODs) in the model. The method for calculating the number of polygons is to gather each model state then count the polygons present in each representation. Animations are not included in the polygon allocation. The RPZ Backflow Device model has a single LOD which is labeled LOD0.

Table 3 Polygon Allocation

Model	# of Triangles	# of Vertices
Glycol Cooling System	5490	3427

3.2 LEVEL OF DETAIL (LODS)

TBD

3.3 TEXTURE MAPS

3.3.1 COLOR MAP

- File name: Glycol_Cooling_System_COL.png (Diffuse)
- Resolution: 4096 x 4096 pixels
- Version: 1.0



Figure 5 Glycol Cooling System Color Map

3.3.2 NORMAL MAP

- File name: Glycol_Cooling_System_NRML.png
- Resolution: 4096 x 4096 pixels
- Version: 1.0




Figure 6 Glycol Cooling System Normal Map

3.3.3 AMBIENT OCCLUSION MAP

- File name: Glycol_Cooling_System_AO.png
- Resolution: 4096 x 4096 pixels
- Version: 1.0



Figure 7 Glycol Cooling System Ambient Occlusion Map

3.4 SENSOR VIEWS

N/A

3.5 MODEL STATES

N/A

3.6 SKELETAL STRUCTURE

N/A

4 ANIMATIONS

N/A

5 VERIFICATION APPROACH

5.1 RUNTIME SYSTEMS

The 3D model was tested using the following tools:

- FBX Viewer 2013.3
- Maya Mental Ray 2016
- Unity 5.3

6 LIMITATIONS

N/A

7 CONTACT INFORMATION

Project Manager: Greg Dukstein

Phone: (407) 601-7847

Email: gdukstein@dignitastech.com